

Table 3 (continued):

Action Code	Action Description
<b>R</b>	Resequence Messages—Resequence the order of messages in a mail basket. All messages will be resequenced in the order of their MailMan internal message identification numbers. <i>(Available with all message readers.)</i>
<b>S</b>	Save Messages to Another Basket—Save messages to another existing mail basket or create a new mail basket. <i>(Available with all message readers.)</i>
<b>T</b>	Terminate Messages—Move messages to the "WASTE" basket and permanently delete the messages from your mailbox. You will <i>not</i> receive further replies to those messages. Messages are not permanently deleted from the system until all recipients of the messages have deleted or terminated them. <i>(Available with all message readers.)</i>
<b>Z</b>	Zoom Selection Toggle (for subsequent group action)—Use this toggle to zoom in and only display <i>selected</i> messages or zoom out and display <i>all</i> messages. This action code is only available when messages have been selected for subsequent group action. <i>(Not available with the Classic message reader.)</i>
<b>=</b>	Refresh Page—The equal sign ("=") tells MailMan to redisplay the basket message list page you were viewing ("refresh" the page/screen). <i>(Not available with the Classic message reader.)</i>
<b>+</b>	Next Page—The plus sign ("+") tells MailMan to go to the next page. This action code is only available when you have more than one "page" of messages when using the Detailed or Summary Full Screen message readers. <i>(Use the Return/Enter key with the Classic message reader.)</i>
<b>+n</b>	Page Forward "n" Pages—The plus sign ("+") before a number ("n") tells MailMan to go forward "n" pages. This action code is only available when you have more than one "page" of messages when using the Detailed or Summary Full Screen message readers. <i>(Use the Return/Enter key with the Classic message reader.)</i>
<b>-</b>	Previous Page—The minus sign ("-") hyphen) tells MailMan to go to the previous page. This action code is only available when you have more than one "page" of messages. <i>(Not available with the Classic message reader.)</i>
<b>-n</b>	Page Back n Pages—The minus sign ("-") hyphen) before a number ("n") tells MailMan to go back "n" pages. This action code is only available when you have more than one "page" of messages. <i>(Not available with the Classic message reader.)</i>

Table 3: Action Codes—Basket Message Lists (continued)

Table 3 (continued):

Action Code	Action Description
<b>0</b>	First Page—A zero tells MailMan to go to the first page. This action code is only available when you have more than one "page" of messages. ( <i>Not available with the Classic message reader.</i> )
<b>?string</b>	Search for messages in the basket whose subject contains the string entered. ( <i>Available with all message readers.</i> )
<b>??string</b>	Search for messages anywhere on the system, which you ever sent or received, whose subject begins with the string entered. ( <i>Available with all message readers.</i> )
<b>^</b>	Exit the List (up-arrow, "^" Shift-6 key on most keyboards)—Exit from the list of messages. ( <i>Available with all message readers.</i> )

Table 3: Action Codes—Basket Message Lists (continued)



**Please remember that not all action codes are available with every message list or with every message reader. Some action codes are only available when certain conditions exist.**



*For a detailed explanation of each action code, please refer to Chapter 2 in the MailMan V. 7.1 & Patch XM\*7.1\*50 User Manual.*